



Proquote International

Quick Setup Guide

Version 1.8
June 2010



London
Stock Exchange

Installation

This requires the user to have administration rights to the local PC as files are installed on the local machine and registry changes are made.

Proquote suggest that the users accept the default installation locations and should they need to change the values that they read the full Proquote International Technical guide.

Connectivity

Proquote International (for clients without a site server) opens a TCP/IP connection to one of Proquote's Data Centers at any one time, however in case of the need to move to a backup data centre we suggest you allow outbound TCP/HTTP connections to all of the sites below.

<u>IP Address</u>	<u>TCP Port</u>
195.26.26.150	4500
195.26.27.150	4500
212.47.180.32	4500

All the IP Address should be entered as below with a space in between each as per below:

Setup - Proquote International

Server Access
To connect to the server please enter one or more internet domain names and a port number.

The list of domain names should be separated by spaces.

Domain(s):
195.26.26.150 195.26.27.150 212.47.180.32

TCP Port:
4500

< Back Next > Cancel

It is also advisable to allow outbound connections to the following additional TCP/HTTP sites which are accessed by some web links within the service.

<u>Service</u>	<u>IP Address</u>	<u>TCP Port</u>
Links Website	212.47.180.54	80
Hemscott	195.26.26.140	1131
Corporate Actions Search	www.proquote.net	80

For optional third party services, TCP/HTTP access to the following domains must be enabled:

<u>Service</u>	<u>IP Address</u>	<u>TCP Port</u>
FTS View	fts.ftsinfo.com	80
Morningstar Quick Take	http://lt.morningstar.com	80
Infinancials	www.infinancials.com	80

PC Prerequisites

	Requirements
Operating System	Microsoft Windows
OS Version	Windows 2000, XP, Vista, Windows 7
Microsoft Office (optional)	Office 2000 - 2007 compatible (DDE, RTD and OLE functions)
Hardware	Intel Xeon (or higher) 2 GHz (or more) 512 MB RAM (or more)
Free Memory	30 MB (or more)

Bandwidth Required

Bandwidth consumption can vary depending on the market focus (high update rate on US markets) and the number of displayed symbols on a Workspace. Below are the recommended bandwidth requirements:

Proquote International - Light user - 128kbps (8 users per Mbps)
Proquote International - Heavy user - 256kbps (4 users per Mbps)

"Light users" don't tend to use much Level 2 data on their screens, they will often be using Level 1 data and the "static data" elements of the product such as fundamentals.

"Heavy users" tend to mainly focus on Level 2 data, often with multiple companies at any point in time.